



Fable

Programming Reference



Updated: 19-12-2017

Contents

Chapter 1: Interface Overview	3
The Fable PC Interface - Blockly	3
The Fable PC Interface - Python	4
Chapter 2: Simple View Blocks	5
Control	5
Senses	5
Camera	6
Actions	6
Data	6
Chapter 3: Full View Blocks	7
Logic	7
Loops	8
Math	9
Colours	9
Lists	10
Variables	10
Functions	11
Senses	12
Camera	13
Actions	14
Data	14
Chapter 4: Python API	15
Joint module	15
Face app	16
Sounds and lights	16
Camera	17
Setup and termination	18
Module handling	18
Time and wait	19
Testing communication	19
Print, plot and data logs	19
Chapter 5: Support Contact	20
Contact	20

Chapter 1: Interface Overview


The Fable PC Interface - Blockly

Users can program their robots by using the Fable software. The interface supports both block-¹ and text-² based programming. The software supports three complexity levels:

Simple: Block based programming for beginner or younger children. A limited number of blocks makes the interface easily accessible.

Full: Blocks based programming for more experienced or older children. Support for more advanced features such as math, functions, logic and variables.

Python: Text based programming using the Python programming language.




¹ Based on Google Blockly

² Based on Python


The Fable PC Interface - Python

The Fable robots can be programmed in Python. Any block program will automatically be translated into Python code which can then be modified and extended by the user.




Chapter 2: Simple View Blocks


Control




Senses




Camera



Actions




Data




Chapter 3: Full View Blocks


Logic




Loops




Math




Colours




Lists




Variables




Functions



Senses



Camera



Actions

Logic

Loops

Math

Colours

Lists

Variables

Functions

Senses

Camera

Actions

Data

Change the light color on a module or dongle (will not change the communication channel).

Playback a standard audio sound on the computer.

Set the angle of motor X and Y that a joint module should move to, the angle is in degrees from -90 to 90.

Set the angle of motor X and Y that a joint module should move to with a given speed. The speed is from 0-100% and the angle is in degrees from -90 to 90.

Ensures subsequent movements with the motors on this joint module will be with the chosen accuracy. At high accuracy the angle of the motors will have a smaller error, but at a high load they can become unstable, i.e. they vibrate.

Set the emotion of the robot's Face app (smartphone app).

Data

Logic

Loops

Math

Colours

Lists

Variables

Functions

Senses

Camera

Actions

Data

Add a data point to a time series plot which will be shown in the interface.

Add data to a log file which is created on your desktop, can be opened e.g. in MS Excel.

Chapter 4: Python API

Quick overview of selected Python functions that can be used to program Fable robots.

Joint module

<code>def setPos(posX, posY, moduleID)</code>	Set the position of a specified joint from -90 to 90 degrees. E.g. <code>api.setPos(45, -60, 'PCA')</code>
<code>def setSpeed(speedX, speedY, moduleID)</code>	Sets speed of a specified joint -100% to 100% percent. Returns an instance of the joint with updated speed values. E.g. <code>api.setSpeed(50, 50, 'YRA')</code>
<code>def setTorque(torqueX, torqueY, moduleID)</code>	Sets the torque for a specified joint. Also sets the torque limit. This value ranges from -100% to 100% percent. E.g. <code>api.setSpeed(50, 50, 'YRA')</code>
<code>def setAccurate(accurateX, accurateY, moduleID)</code>	Modify the motor controller (compliance slopes, margins and punch) for the X and Y joint motors to make them move more accurate. E.g. <code>api.setAccurate('HIGH', 'DEFAULT', 'YRA')</code>
<code>def getPos(motorID, moduleID)</code>	Returns the position of one of the motors from a joint. The encoder has a resolution of 0.29 degrees. Motors can move from -90 to 90 degrees. E.g. <code>x = api.getPos('X', 'YRA')</code>
<code>def getSpeed(motorID, moduleID)</code>	Returns percentage representation from -100% to 100% of speed for one of the two motors from a specified joint. Note: is derived from the position sensor. E.g. <code>x = api.getSpeed('Y', 'YRA')</code>
<code>def getTorque(motorID, moduleID)</code>	Returns percentage representation from -100% to 100% of torque used by one of the two motors from a specified joint. Note: is derived from current flow in motors. <code>x = api.getTorque('Y', 'YRA')</code>
<code>def getMoving(motorID, moduleID)</code>	If a motor of a specified joint moves it returns True. E.g. <code>if api.getMoving('Y', 'YRA'): api.output('It is moving!')</code>

<code>def getTemperature(motorID, moduleID)</code>	Returns the temperature of one of the two motors from a specified joint module (in degrees Celsius). E.g. <code>api.getTemperature('Y', 'QQA')</code>
<code>def getBattery(moduleID)</code>	Returns the battery level of a specified module. Returns number representation of battery level. E.g. <code>api.getBattery('QQA')</code>

Face app

<code>def setFaceEmotion(emotion)</code>	Set the emotional state in the Face. Valid arguments: 'Neutral':0, 'Happy': 1, 'Sad': 2, 'Angry': 3, 'Tired': 4 E.g. <code>api.setFaceEmotion('Sad')</code>
<code>def getFaceEmotion()</code>	Get the emotional state of the Face. Returns int as Emotional state, e.g. 1 for 'Happy'. E.g. <code>api.getFaceEmotion()</code>
<code>def getFaceAcceleration(direction)</code>	Get the acceleration of the smartphone running the face app. Valid directions are 'X', 'Y' or 'Z'. Returns acceleration of the selected axis in SI units e.g. `5.124` m/s^2. E.g. <code>api.getFaceAcceleration('X')</code>

Sounds and lights

<code>def getSoundLevel(milliseconds = 50)</code>	Returns the microphone sound level in RMS (default windows used is 50ms). E.g. <code>api.getSoundLevel()</code>
<code>def playBeep(frequency, duration, channel)</code>	Plays back a beep with a given frequency (Hz) for a given duration in seconds on a give channel (0-9). E.g. <code>api.setColor([255, 0, 0], 'QQA')</code>

<code>def playSound(filename)</code>	Play back a sound file from the installation folder: Fable\resources\app\app\sounds E.g. api.playSound('angry.wav')
<code>def setColor(color, moduleID)</code>	Sets light color to a specified module/dongle. The color is an RGB list of numbers scaled from 0-255. E.g. api.setColor([255, 0, 0], 'QQA')

Camera

<code>def takePicture()</code>	Save a picture from the camera, in folder "Fable pictures\" on the desktop E.g. api.takePicture()
<code>def foundSimpleColor(color)</code>	Looks in the image for a specific blob of color. Returns true if it finds it. E.g. api.foundSimpleColor([102, 255, 51])
<code>def foundAdvancedColor(color, nuances, size)</code>	Looks in the image for a specific blob. Returns true if the color is found. Nuances of the color to include (from 0 to 20). Size is the minimum size of the colored object compared to the image (in percentage). E.g. api.foundAdvancedColor([153, 102, 255], 10, 30)
<code>def getSimpleColorCenter(color)</code>	Returns an (x, y) list of the position of the colored blob in the image. (0, 0) is at the center. x and y scales from -100 to 100. E.g. api.getSimpleColorCenter([255, 0, 255])[0]
<code>def getAdvancedColorCenter(color, nuances, size)</code>	Returns an (x, y) list of the position of the colored blob in the image, with a minimum size and a range of nuances. (0, 0) is at the center. x and y scales from -100 to 100. E.g. api.getAdvancedColorCenter([0, 255, 204], 10, 30)[1]

<code>def detectedMotion(threshold)</code>	Returns True if motion is found. Threshold is the minimum amount of motion in the image (in percentage) required to trigger a detection. E.g. <code>api.detectedMotion(2)</code>
<code>def getMotionCenter(threshold)</code>	Returns an (x, y) list of the motion center. (0, 0) is at the center of the image. Threshold is the minimum amount of motion in the image (in percentage) required to trigger a detection. E.g. <code>api.getMotionCenter(2)[0]</code>

Setup and termination

<code>def setup(defaultPort=None, blocking=False)</code>	Setup the API and tries to connects to a dongle. If blocking=True it will not terminate before a dongle is connected. E.g. <code>api.setColor([255, 0, 0], 'QQA')</code> Note: This function should only be used when programming standalone, not in Fable interface.
<code>def terminate()</code>	Stops the dongle and sends a command to all modules to go to their default state. E.g. <code>api.terminate()</code> Note: This function should only be used when programming standalone, not in Fable interface.

Module handling

<code>def discoverModules()</code>	Checks for connected modules and populates a list with their details. Returns a list of found module IDs. E.g. <code>api.discoverModules()</code> Note: This function should only be used when programming standalone, not in Fable interface.
<code>def getModuleIDs()</code>	Returns a list of all module IDs seen. E.g. <code>api.getModuleIDs()</code>

Time and wait

<code>def getTime()</code>	Returns time elapsed since start of the program, in seconds. E.g. <code>api.getTime()</code>
<code>def wait(seconds)</code>	Creates a pause in the program for a given amount of seconds. E.g. <code>api.wait(0.1)</code>

Testing communication

<code>def getConnectionQuality(moduleID)</code>	Returns the connection quality of a specified module. E.g. <code>api.getConnectionQuality('QQA')</code>
<code>def checkDongleConnection()</code>	Checks dongle connection. Returns true if dongle is connected. E.g. <code>api.checkDongleConnection()</code>

Print, plot and data logs

<code>def output(*args)</code>	Print out data received as arguments in the output window. E.g. <code>api.output('Hello World', 5)</code> Note: This function should only be used when programming in the Fable interface, not standalone (use <code>print('Hello World', 5)</code> instead).
<code>def plot(data, label, windowSize = 50, windowTime = 2.5)</code>	Draws a time series plot. Adds a datapoint to the plot which will be shown in the interface. E.g. <code>api.plot(100, 'A')</code> Note: This function should only be used when programming in the Fable interface, not standalone (use <code>print('Hello World', 5)</code> instead).
<code>def log(data, filename = 'log.csv')</code>	Writes data to a log file which is placed on the desktop. E.g. <code>api.log(100, 'A')</code>

Chapter 5: Support Contact

Contact

Support information are available online at <http://shaperobotics.com>

For personalized support contact Shape Robotics at: support@shaperobotics.com